

ONE SHEET WONDER



SUPPLIES FOR ALL CARDS

Stamp: Something to Say

Paper: Park Lane Designer Series Paper, Whisper White, Sahara Sand, Soft Suede

Ink: Soft Suede

Other: Daffodil Delight ¼" Cotton Ribbon, Whisper White Bakers Twine, Scallop Edge Border Punch, Itty Bitty Accents Punch Pack, Neutrals Candy Dots

CHOOSING YOUR PAPER

1. Select one sheet of Designer Series Paper as your primary (focal) paper. **Tip:** This technique works best with paper that has a large-scale, all-over design. It also helps if the paper doesn't have an obvious direction (i.e. words/images that can only be viewed one way). For my cards, I chose the sheet with the floral images.
2. Select one sheet of the Designer Series Paper as your secondary paper. **Tip:** This technique works best if this sheet has a medium- to small-scale print and has colors that are included in the focal paper. For my cards, I chose the Soft Suede chevron print.
3. Select a neutral solid color cardstock for your card bases (Solid Color A). I chose Sahara Sand.

Cindy Techlin, Stampin' Up! Independent Demonstrator

www.StampinAnInkTrail.blogspot.com

Email: ctechlin2@new.rr.com

4. Select a second solid color cardstock for your layers (Solid Color B). I chose Soft Suede.
5. I also used scraps of 2 other sheets of DSP included in the Park Lane paper pack for various layers/banners.

CUTTING

1. There are three different cutting diagrams – one for your focal paper, one for your secondary paper and one for Solid Color B (3 sheets). Cut your paper using the coordinating paper/diagram. Use the **blue** lines on the cutting diagram for your 1st cut. If there is a **green** line on the diagram, that should be your 2nd cut. Any areas shaded in peach are scrap and not needed for the cards. **Tip:** Label the back of your pieces with the letter noted in the diagram. This will help during assembly of the cards.
2. You can precut your card bases using Solid Color A. However, DO NOT pre-fold your card bases. There are **10** different folds used for these cards. The folding technique will be included with the individual card instructions. You will need the following:
 - a. 4 ½ x 11 (Cut 8 ½ x 11 in half vertically) – Cut 7
 - b. 5 ½ x 8 ½ (Cut 8 ½ x 11 in half horizontally) – Cut 8

SENTIMENTS/EMBELLISHMENTS

1. Sentiments are stamped on Whisper White cardstock using Soft Suede ink. The Whisper White cardstock is cut to two different sizes: 1 ½" square and 2 ½ x ¾".
2. The longer, one-line sentiments are stamped on the 2 ½" x ¾" pieces. The other sentiments are stamped on the 1 ½" square pieces.
3. Layer the square sentiments on Solid Color B cardstock cut to 1 ¾" square.
4. The flowers are stamped in Soft Suede ink on the Daffodil Delight DSP from the Park Lane DSP. They are punched using the coordinating punch from the Itty Bitty Accents Punch Pack.

OTHER IDEAS

1. You could stamp your own focal paper. Use three or four different images and ink colors to create your own pattern. Rotate the paper and images as you stamp to create a non-directional pattern. Coordinate with paper from a DSP stack or solid color cardstock.
2. Stamp sentiments on cardstock but do not adhere to card until you know what occasion you will use the card for.

CARD A – GATE FOLD CARD



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 2 ¼" and 7"
3. Fold on the score lines toward the center

INSTRUCTIONS

1. Layer and adhere focal paper to Solid Color B.
2. Adhere all pieces to the card base.
3. Stamp 2 coordinating sentiments.
4. Arrange sentiments vertically over the seam of the gate fold. Place dimensional adhesive on the left side of the top sentiment and the right side of the bottom sentiment. Adhere to card.

CARD B



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. From coordinating DSP, cut piece 3 ¼" x 3 ¾".
2. Layer and adhere all pieces to Solid Color B according to the photo. Do not attach to card base.
3. Using a ½" x 3 ¾" scrap of Solid Color B, punch using the Scallop Edge Border Punch to create the trim.
4. Wrap Whisper White Bakers Twine around layer twice. Tie bow.
5. Adhere to card base.
6. Add sentiment and embellishment.

CARD C



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. Layer and adhere focal paper to Solid Color B.
2. Cut banners measuring ½" x 3 ½" and ½" x 3 ¾" using two different scraps of coordinating DSP.
3. Arrange banners on card base. Overlap focal paper layer slightly as shown in photo.
4. Adhere to card base.
5. Add sentiment and embellishment.

CARD D – EASEL CARD



CARD BASE

1. Size: 4 ¼" x 11"
2. Score: 2 ¾" and 5 ½"
3. Fold on both score lines. See photos.

INSTRUCTIONS

1. Punch both edges of Solid Color B with the Scallop Edge Border Punch.
2. Layer focal paper in the center of Solid Color B.
3. Cut layer measuring 5 ½" x 4" using coordinating DSP.
4. Cut piece of Solid Color A measuring 5 ½" x 4".
5. Adhere all pieces to Solid Color A layer from Step 4 as shown in photo.
6. Using the piece created in Step 5, adhere to card base. Only attach layer to card base below the 2 ¾" score line.
7. Stamp two coordinating sentiments. Attach first sentiment to card front. Attach the second sentiment to the inside of the card using dimensional adhesive. This is what holds the easel in place when open.

CARD E – TENT CARD



CARD BASE

1. Size: 4 ¼" x 11"
2. Cut card base to 4 ¼" x 8 ½"
3. Score: 4 ¼"
4. Fold in half on the score line

INSTRUCTIONS

1. Adhere secondary DSP to the center of card base.
2. Cut piece of Solid Color A measuring 3 ¼" x 4 ½".
3. Adhere Solid Color B and focal paper to the piece cut in Step 2.
4. Wrap Daffodil Delight Cotton Ribbon around layer. Tie a bow.
5. Using the piece created in previous steps, apply adhesive to lower half of layer and attach to card base. **Tip:** When adhering layer to card base, check that the overall height of card does not exceed 5 ½". This will allow card to fit in standard envelope.
6. Add sentiment and embellishment.

CARD F



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. Adhere secondary DSP to lower portion of card base.
2. Punch short edge of Solid Color B with the Scallop Edge Border Punch.
3. Adhere focal paper to Solid Color B.
4. Wrap Daffodil Delight Cotton Ribbon around layer. Tie bow.
5. Adhere to card base.
6. Add sentiment and embellishment.

CARD G



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. Adhere focal paper to Solid Color B.
2. Cut layer measuring 3" x 4 ½" using coordinating DSP.
3. Cut banner measuring 1" x 1 ¼" using a second coordinating DSP.
4. Arrange pieces as shown in photo.
5. Adhere to card base.
6. Add sentiment and embellishments.

CARD H – Z-FOLD CARD



CARD BASE

1. Size: 4 ¼" x 11"
2. Score: 2 ¾" and 5 ½"
3. Fold on both score lines. See photos.

INSTRUCTIONS

1. Adhere 2 ¾" x 4 ¼" Solid Color B piece and secondary DSP to card base.
2. Cut piece of Solid Color A measuring 3 ½" x 4 ¼".
3. Adhere Solid Color B and focal paper to layer cut in Step 2.
4. Wrap Daffodil Delight Cotton Ribbon around layer. Tie bow.
5. Using the piece created in Step 5, adhere to card base. Apply adhesive to half of layer and attach to card base. **Tip:** Do not apply adhesive to entire top layer as that will adhere the card shut.



CARD I



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. Cut banners measuring ½" x 4 ¾" and ¾" x 5" using two different scraps of coordinating DSP.
2. Arrange banners on secondary DSP. Adhere banners together.
3. Wrap Whisper White Bakers Twine around banners and tie bow.
4. Adhere to card base.
5. Layer focal paper to Solid Color B. Adhere to card base.
6. Add sentiment and embellishment.

CARD J



CARD BASE

1. Size: 5 ½" x 8 ½"
2. Score: 4 ¼"
3. Fold in half on the score line

INSTRUCTIONS

1. Cut banners measuring 1" x 3 ¾" and ¾" x 4" using two different scraps of coordinating DSP.
2. Cut banner tail on secondary DSP.
3. Arrange all banners and adhere to card base.
4. Layer focal paper to Solid Color B.
5. Adhere to card base.
6. Add sentiment and embellishments.

CARD K – TOP FOLD CARD



CARD BASE

1. Size: 4 ¼" x 11"
2. Score: 2 ½" and 6 ¾"
3. Fold on both score lines. See photos.
4. Using a 2 ½" Circle Punch, line up score line at 2 ½" in center of punch and punch a circle.

INSTRUCTIONS

1. Adhere 2 ¾" x 4" Solid Color B piece and secondary DSP to card base.
2. Adhere 2" x 3 ¾" focal paper and 2 ¼" x 4" Solid Color B to card base. For the portion that overlaps the circle cut in the card base, use 2 ½" Circle Punch and remove that piece.
3. Using Solid Color B, punch a piece using the 2 3/8" Scallop Circle Punch
4. Attach Scallop Circle with dimensional adhesive to card base.
5. Punch a piece of coordinating DSP using the 2" Circle Punch.
6. Punch a piece of Whisper White using the 1 ¼" Circle Punch. Stamp sentiment on circle.
7. Adhere circles punched in Steps 5 & 6 to the Scallop Circle in Step 4.

CARD L



CARD BASE

1. Size: 4 ¼" x 11
2. Score: 5 ½"
3. Fold in half on the score line

INSTRUCTIONS

1. Adhere focal paper to Solid Color B.
2. Wrap Daffodil Delight Cotton Ribbon around layer. Tie bow.
3. Using a ½" x 4 ½" scrap of coordinating DSP, punch using the Scallop Edge Border Punch to create the trim.
4. Using the secondary DSP, cut a banner tail on the 1" end.
5. Arrange on card front as shown in photo
6. Adhere to card base.
7. Add sentiment and embellishment.


CARD M – FRONT STEP CARD



CARD BASE

1. Size: $5\frac{1}{2}'' \times 8\frac{1}{2}''$
2. Score: See Diagram
3. Cut: See Diagram

Front Step Card - Cut and Score Lines



INSTRUCTIONS

1. Adhere secondary DSP across bottom of card.
2. Cut 2 pieces of coordinating DSP $1'' \times 3''$ and adhere to the side folds of card base.
3. Adhere focal paper to Solid Color B.
4. Wrap Daffodil Delight Cotton Ribbon around layer from Step 3. Tie bow.
5. Attach Solid Color B panel to center panel of card base.

CARD N – DOUBLE DUTCH FOLD CARD




CARD BASE

1. Size: 4 ¼" x 11"
2. Cut card base to 4 3/16" x 9 ¼"
3. Score: 5 ½"
4. Cut second piece of Solid Color A – 2" x 8 ½"
5. Score: 2 1/8" and 6 3/8"
6. Layer first piece in the center of second piece and adhere on the back.
7. See Tutorial if you need more information:
<http://www.splitcoaststampers.com/resources/tutorials/doubledutchfold/>

INSTRUCTIONS

1. Using the Scallop Edge Border Punch, punch the 4 3/16" edge of the 4 3/16" x 9 ¼" card base.
2. Adhere focal paper to Solid Color B.
3. Wrap Whisper White Bakers Twine around layer from Step 2. Tie bow.
4. Attach Solid Color B panel to center panel of card base.
5. Adhere secondary DSP to lower panels of card base.
6. Add sentiment and embellishment.

CARD O – JOY FOLD CARD



CARD BASE

1. Size: 4 ¼" x 11"
2. Cut card base to 4 ¼" x 8 ½"
3. Score: 5 ½"
4. Cut second piece of Solid Color A – 3" x 8"
5. Score: 4"
6. See Tutorial if you need more information:
http://www.splitcoaststampers.com/resources/tutorials/joy_fold_card/

INSTRUCTIONS

1. Adhere your 4" x 5 ¼" piece of secondary DSP on the inside of the card.
2. Adhere your 2 ½" x 3 ½" piece of focal paper to Solid Color B layer. Adhere to smaller card base.
3. Cut a piece of coordinating DSP to 2 ¾" x 4" and adhere to main card base panel. See photo.
4. Add adhesive to the back of the smaller card base and adhere it to the main card base. Make sure the fold of the smaller flap is pointing to the right.
5. Wrap Whisper White Bakers Twine around front card panel. Tie bow.
6. Add sentiment and embellishment.

